## **Troubleshooting Checklist for Photo Uploads**

## 1. Photo and File-Related Issues

- Check the photo's file type. The website only accepts specific JPG, JPEG, or PNG. If the photo is in a less common format (like HEIC from an iPhone), the system might not be able to process it, leading to an error.
  - Solution: Convert the photo to a compatible format. This can be done with a photo editor or a free online file converter.
- Review the photo's file size. Large, high-resolution photos can "time out" during upload, especially with a slow internet connection. The website has a file limit of 1 gigabyte, for others to see photo, please keep file size to 2mb if possible.
  - Solution: Reduce the file size. This can be done by compressing the image or by resizing it using photo editing software.
- Check the file name. File names with special characters (\$%^&\*) or long strings of text can sometimes cause issues with a website's code.
  - Solution: Rename the file to something simple, using only letters, numbers, and hyphens (e.g., my-fishing-photo.jpg).
- Ensure the photo is not corrupted. A file that is corrupted can fail to upload.
  - Solution: Try opening the photo in a different program on your computer or mobile device. If it won't open, the file may be corrupted. Try using a different photo.
- Avoid using photos from social media. Photos copied from sites like Facebook or Instagram are often low-quality and have a different format that can cause issues.
  - Solution: Use the original photo file taken from your camera or phone.

## 2. Browser and Computer-Related Issues

- **Try a different web browser.** Sometimes, a specific browser can have a conflict with a website.
  - Solution: If the user is using Chrome, suggest they try Firefox or Safari, and viceversa.
- Clear the browser's cache and cookies. Outdated cached data can sometimes interfere
  with a website's functionality and prevent a new upload from being processed correctly.

- Solution: In the browser's settings, find the option to clear browsing data and clear the cache and cookies for a specific time range.
- **Disable browser extensions.** Certain extensions, especially ad-blockers or privacy extensions, can sometimes block scripts that are essential for the upload process.
  - o **Solution:** Temporarily disable all browser extensions and try the upload again.
- **Restart the computer or phone.** A simple reboot can often resolve minor software glitches that may be causing the issue.

## 3. Network and Connectivity Issues

- Check your internet connection. A slow or unstable internet connection can cause the upload to fail, especially with larger files.
  - Solution: Run an internet speed test to check your upload speed. If it's very low, try moving closer to your Wi-Fi router or restarting it. Try checking the website with speedtest.net
- **Switch networks.** If possible, try uploading the photo using a different Wi-Fi network or by switching to your mobile data. This will help determine if the issue is with your local network.

By following these steps, users can often resolve the white-screen error and successfully upload their photos.